



GE VERNOVA

Grid Solutions

Reason DR Manager

Software version 9.3.0 Release Notes

Copyright © 2024 GE Vernova

Overview

GE Vernova regularly introduces software updates to address enhancements in different functional areas. This release includes the following:

- fixing a storage issue related to downloading DR60 configuration;
- including login by user and password in RPV311 to allow communicate with FW15A00;
- fixing bugs in Alarms tab;
- update release versioning based on current format;
- GE Vernova rebranding.

Software Release Date: **November 2024**

Software Upgrade Process

Upgrading to Reason DR Manager 9.3.0 can be done by executing “ReasonDRManager.InstallerWizard.exe” as administrator, after extracting the “DRManager9.3.0.zip” file.

Software version 09A00 and 9.1.4 can be upgraded without updating the database.

If you have DR Manager version 08A02 or lower than an update of the database is necessary. This process is automated by the installer wizard, please follow the steps indicated by the software. We advise to backup your database using Reason DR Manager before the procedure.

FW Compatibility

This software version is not compatible with DR60 firmware version 02A04 and below. The software will not communicate to DR60 with previous firmware versions until user update the firmware. Users need to configure username and password for each device on the Reason DR Manager, on the menu Settings -> Device.

This software version is compatible with RPV311 firmware version 09A00 and above.

Please contact your local sales representative or Grid Automation Global Contact Center for any questions regarding this upgrade.

Release details

In the following release description, a revision category letter is placed to the left of each topic. Refer to the Appendix at the end of this document for the categories displayed.

General improvements

E Fixing a storage issue related to downloading DR60 configuration;

When a DR60 is included in the device lists the DR Manager check the current configuration of the device, this proceeding is repeated all refresh cycle. During this process the configuration files of the DR60 were saved in a *temp* folder and they weren't deleted after usage. This fix remove the files after the usage.

E Including login by user and password in RPV311 to allow communicate with FW15A00;

In the new FW version of the RPV311 was changed the authentication access, for this reason was included the access by user and password.

E Fixing bugs in Alarms tab

The Alarm tab was fixed to present real status of the RPV311. This issue was verified when the alarm "Class C chain OK" was added. This alarm has inverted logic, when the Sync is OK, this alarm is activated. This fix inverted this logic alarm in DR Manager, and the Green, Yellow, Red and White colors present the real status of the device.

G Update release versioning based on current format

This fix doesn't affect user interface.

G GE Vernova Rebranding

This fix doesn't affect user interface.

Appendix

Change categories

This document uses the following categories to classify the changes.

Table 1: Revision Categories

Code	Category	Comments
N	New feature	A separate feature added to the product. Changes to existing features even if they significantly expand the functionality are not in this category
G	Change	A neutral change that does not bring any new value and is not correcting any known problem
E	Enhancement	Modification of an existing feature bringing extra value to the application
C	Protocols and communications	Changes to, or problems with protocols or communication features
B	Unexpected restart	Product restarts or closes unexpectedly

For further assistance

For questions or further product support, please contact the GE support team using:

Region	E-mail	Telephone
Global Contact Centre	GA.support@GE.com	+44 1785 250070
Central, East Asia, Pacific	GA.supportCEAP@GE.com	+61 414 730 964
India	GA.supportIND@GE.com	+91 44 2264 8000
Middle East, North Africa, Turkey	GA.supportMENAT@GE.com	+971 4 375 6950
Europe, Russia, CIS, Sub-Saharan Africa	GA.supportERCIS@GE.com	+34 94 485 8854
North America	GA.supportNAM@GE.com	+1 877 605 6777